



Adobe AIR SDK Release Notes

Version	51.1.1.5
Date	17 September 2024
Document ID	HCS19-000287
Owner	Andrew Frost

Table of contents

1	Release Overview	3
1.1	Key changes	3
1.2	Deployment	4
1.3	Limitations	4
1.4	Feedback	4
1.5	Notes	4
2	Release Information	6
2.1	Delivery Method	6
2.2	The Content of the Release	6
2.3	AIR for Linux – Restrictions	7
2.4	AIR for Flex users	7
3	Summary of changes	8
3.1	Runtime and namespace version	8
3.2	Build Tools	8
3.3	AS3 APIs	8
3.4	Features	8
3.5	Bug Fixes	13
4	Configuration File	27
5	Android builds	29
5.1	AAB Target	29
5.2	Play Asset Delivery	29
5.3	Android Text Rendering	30
5.4	Android File System Access	31
6	Windows builds	33
7	MacOS builds	34
8	iOS support	35
8.1	32-bit vs 64-bit	35
8.2	MacOS remote linking from Windows	35
9	Splash Screens	38
9.1	Desktop (Windows/macOS)	38
9.2	Android	38
9.3	iOS	38

1 Release Overview

Release 51.1.1.1 starts a new major/minor category of 51.1, with additional settings being added to the application descriptor file, and a number of new features being introduced. No changes have been made to the ActionScript APIs or versioning, so the SWF version for this continues to be 51.

Release 51.1.1.2 contains a small number of critical bug fixes that had been found in 51.1.1.1. Updates for release 51.1.1.2 are displayed in a dark red font.

Release 51.1.1.3 has a few further key fixes; updates are displayed in a blue font.

Release 51.1.1.4 includes key fixes for Encrypted Local Store plus some other functionality, and is shown in an olive green font.

Release 51.1.1.5 is provided primarily for Android and Linux platforms, with some updates also on Windows; however, macOS and iPhoneOS targets have not been updated – the next release for those will be 51.2 to support the latest Xcode and macOS/iOS SDK versions. Changes related to 51.1.1.5 are shown in an orange font.

1.1 Key changes

The changes are fairly wide-ranging: one key change for Android users is that the target SDK API value is now set to 34 by default, removing the need to explicitly set this within your application descriptor file. Internally the build processes have also been updated to this, with a number of deprecated functions no longer being used.

Another update for Android is on the ANE side, where it is now possible to have a single “Android” platform definition (unless using native/JNI shared libraries) where this can then be set to include either a JAR file as previously supported, or an AAR file.

For Android TV, support has been added for the variable icon and banner sizes, with ADT automatically adjusting to use the different icon sizes for each resolution category for applications that are specified as supporting Android TV.

The AS3 compiler has been updated, to fix a bug in ‘debugline’ instruction generation, to allow developers to restrict the ABC versioning/functionality to remove ‘float’ support, and to add support for a Unicode character definition of the form “\u{nnnnnn}” where ‘nnnnnn’ is a full Unicode character code that will be split into a surrogate pair of UTF-16 character codes if necessary.

There are a number of other fixes and updates, see sections 3.4 and 3.5 for details.

Bug fixes for 51.1.1.2 can be found in section 3.5.2.

Bug fixes for 51.1.1.3 can be found in section 3.5.3. The main fix is for iOS18 where a change in Apple’s font file format meant that Chinese fonts were being rejected by AIR; this update should allow Chinese character rendering again.

There are a number of key updates in 51.1.1.4, including around the Encrypted Local Store functionality which had been causing problems in earlier 51.1 builds due to changes in how this worked. The default timestamp server for signing some platforms has also been updated due to the retirement of the older server. Plus some other bug fixes which can be found in section 3.5.4.

51.1.1.5 continues with additional updates for Encrypted Local Store, which we hope will be the last updates required in order to make this more future-proof. Some updates were also required in the build tools to ensure macOS applications are correctly packaged, and in the Linux runtime to fix some

timezone-related problems. The other changes around Android will improve the user experience around text fields including to ensure an 'escape' key press is passed into the AS3. Changes related to this release can be found in section 3.5.5.

1.2 Deployment

To obtain the release, it is recommended that developers install the AIR SDK Manager. Whilst the monolithic zip files will still be available from the <https://airsdk.harman.com> website, this may be updated less frequently in the future with only major releases. The goal is for the AIR SDK Manager to help us publish minor updates/fixes with a quicker cadence without resulting in a large amount of effort and data downloads.

The AIR SDK Manager is now available from the <https://airsdk.dev> website, as part of the "getting started" instructions, or directly from github at: <https://github.com/airsdk/airsdkmanager-releases>

1.3 Limitations

For macOS users on 10.15+, the SDK may not work properly unless the quarantine setting is removed from the SDK: `$ xattr -d -r com.apple.quarantine /path/to/SDK`

Please note that there is no longer support for 32-bit IPA files, all IPAs will use just 64-bit binaries now so older iPhones/iPads may not be supported.

Android development should now be performed with an installation of Android Studio and the SDK and build tools, so that the new build mechanism (using Gradle and the Android Gradle Plug-in) can use the same set-up as Android Studio.

Linux runtimes are built using Ubuntu 16 for x86_64 variants in order to provide maximum compatibility; however for arm64, the build environment uses Ubuntu 22 which then restricts usage to similar versions of Linux (i.e. that have glibc version 2.34 or later).

1.4 Feedback

Any issues found with the SDK should be reported to adobe.support@harman.com or preferably raised on <https://github.com/airsdk/Adobe-Runtime-Support/issues>.

The website for AIR SDK is available at: <https://airsdk.harman.com> with the developer portal available under <https://airsdk.dev>

1.5 Notes

Contributors to the <https://airsdk.dev> website would be very welcomed: this portal is being built up as the repository of knowledge for AIR and will be taking over from Adobe's developer websites

The AS3 documentation for AIR is updated and now also available under this site: <https://airsdk.dev/reference/actionsript/3.0/>

We will continue to provide the shared AIR runtime for Windows/macOS; however, this is not a recommended deployment mechanism, it is preferable to create native installers based on the "bundle" deployments.

On MacOS in particular, the use of the shared AIR runtime to 'install' a .air file will not create a signed application, hence new MacOS versions may block these from running. To ensure a properly signed MacOS application is created, the "bundle" option should be used with native code-signing options



(i.e. those appearing after the “-target bundle” option) having a KeychainStore type with the alias being the full certificate name.

2 Release Information

2.1 Delivery Method

This release shall be delivered via the AIR SDK website: <https://airsdk.harman.com/download>

The update will also be available via the AIR SDK Manager. The latest version of this can be downloaded from <https://github.com/airsdk/airsdkmanager-releases/releases>.

2.2 The Content of the Release

2.2.1 Detailed SW Content of the Release

Component Name	51.1.1.1	51.1.1.2	51.1.1.3	51.1.1.4	51.1.1.5
Core Tools	3.2.0	3.2.1	3.2.2	3.2.3	3.2.4
AIR Tools	3.0.0			3.1.0	
Windows platform package	3.2.0	3.2.1	3.2.2	3.2.3	3.2.4
MacOS platform package	3.2.0	3.2.1	3.2.2	3.2.3	
Linux platform package	3.2.0	3.2.1	3.2.2	3.2.3	3.2.4
Android platform package	3.2.0	3.2.1	3.2.2	3.2.3	3.2.4
iPhone platform package	3.2.0	3.2.1	3.2.2	3.2.3	

2.2.2 Delivered Documentation

Title	Document Number	Version
Adobe AIR SDK Release Notes	HCS19-000287	51.1.1

2.2.3 Build Environment

Platform	Build Details
Android	Target SDK Version: 34 Minimum SDK Version: 21 Platform Tools: 28.0.3 Build Tools: 34.0.0 SDK Platform: Android-34 Note – these are the versions we use to build the AIR SDK and runtime, we also recommend developers match the same ‘target SDK’ version as here.
iOS	iPhoneOS SDK Version: 17.5 iPhoneSimulator SDK Version: 17.5 XCode Version: 15.4 Minimum iOS Target: 12.0

tvOS	tvOS SDK Version:	17.5
	tvSimulator SDK Version:	17.5
	XCode Version:	15.4
	Minimum tvOS Target:	12.0
MacOS	MacOS SDK Version:	14.5
	XCode Version:	15.4
	Minimum macOS Target:	10.13
Windows	Visual Studio Version:	14.0.25431.01 Update 3
Linux	GCC Version	5.4.0 (Ubuntu 16.04.1 – x86_64) 11.4.0 (Ubuntu 22.04.3 – arm64)

2.3 AIR for Linux – Restrictions

The AIR SDK now supports both x86_64 and arm64 based Linux platforms. These are only available to developers with a commercial license to the SDK, and have some restrictions:

- No “shared runtime” support: applications would need to be built as ‘bundle’ packages with the captive runtimes
- Packaging into native installers (“native” target type for .deb or .rpm files) is currently not working: please create a “bundle” target and use Linux tools to distribute these
- No “StageWebView” component.

2.4 AIR for Flex users

HARMAN have continued Adobe’s strategy of issuing two AIR SDKs per platform: the first of these (“AIRSDK_[os].zip”) contains the newer ActionScript compiler and is a full, self-contained SDK for compiling and packaging AIR applications. The second of these is for combination with the Flex SDK (“AIRSDK_Flex_[os].zip”) which doesn’t include a number of the files necessary for ActionScript/MXML compilation. These SDKs should be extracted over the top of an existing, valid Flex SDK.

The original instructions from Adobe are at <https://helpx.adobe.com/uk/x-productkb/multi/how-overlay-air-sdk-flex-sdk.html> but a few alterations to this are needed to Step 4 if running on macOS. For this platform, the downloaded AIR SDK zip needs to be expanded to a temporary area and then the copy command needs to copy symbolic links as links rather than resolving them to files. This can be done using a capital ‘R’ rather than lowercase, hence:

```
cp -Rf /tmp/AIRSDK_Flex_MacOS/* /path-to-empty-FLEXSDK-directory
```

Please note that the config files (air-config.xml, airmobile-config.xml, flex-config.xml) may need to be updated to support new features and updates in AIR or in dependencies such as ANEs. For example to ensure the correct SWF version is output, the below line would need to be updated (e.g. to ‘50’ for AIR 50.x, or ‘44’ for AIR 33.1, etc):

```
<swf-version>14</swf-version>
```

3 Summary of changes

3.1 Runtime and namespace version

Namespace: 51.1

SWF version: 51

The namespace and SWF version updates are made across all platforms and may be used to access the updated ActionScript APIs that have been introduced with AIR version 51.0. The namespace update is required for opening any SWF file that's got a SWF version of 51, or when using any of the new XML application descriptor flags.

3.2 Build Tools

The Android build tools and platform used to create the AIR runtime files has been updated to Android-34 with the default target SDK now set to this level in the generated Android manifest files.

Xcode 15.4 and the latest macOS and iPhoneOS/tvOS SDKs are now being used to build the AIR SDK. Please note when the update was made to use Xcode 15.0, the minimum iOS/tvOS target version was increased to 12. Additional note: these are the versions that AIR itself is built with. The versions shown in IPA files are manually injected by ADT and don't (yet) take the version codes from the local build environment. See [Issue #3030 \(github.com\)](#).

The build system for this is on a version of macOS that doesn't support 32-bit processes hence we cannot generate the 32-bit versions of the stub files. This means that we can no longer support older 32-bit iPhone/iPad devices.

3.3 AS3 APIs

No changes.

3.4 Features

Reference:	AIR-6196
Title:	Allowing ANEs for Android to have a single platform
Applies to:	Core build tools
Description:	When packaging an ANE for Android, if it just uses Java code, there is no longer a need to specify the different platforms for different CPU variants, i.e. Android-ARM64 etc. A single "Android" platform can now be used for Java-based Android ANEs.

Reference:	AIR-6197
------------	-----------------



Title:	Ability to use AAR files for Android ANEs
Applies to:	Core build tools
Description:	As well as using a JAR file, it's now possible to use an AAR file for Android ANEs. This will be expanded and the classes plus resources will be packaged into the ANE for use by the application.

Reference:	AIR-6679
Title:	AIR app bundle creation to use architecture option
Applies to:	Core build tools
Description:	For macOS application bundle creations, the "-arch" option can be used in ADT to determine whether the output bundle contains "x64" (x86_64) binaries only, or "armv8" (arm64) binaries, or (if omitted, by default) the existing output which contains universal binaries (x86_64 and arm64).

Reference:	AIR-7069
Title:	AIR URL requests should include app-id in a custom header
Applies to:	All runtime components
Description:	When a URL request is made from AIR, a number of headers are included in the HTTP request; this change adds a new one "x-air-appid" which has a SHA-256 hash of the AIR's Application ID. This is intended to help server code to ensure the correct application is accessing resources.

Reference:	AIR-7114
Title:	Ability to turn off rotation animations for AIR apps with 'orientationAnimation'
Applies to:	Android and iOS runtime components, core build tools

Description:	<p>A new flag in the 'initialWindow' section of the application descriptor file can be used to turn off the animations that are seen when a user rotates a phone (assuming "autoOrients" is set to "true"). The default is "standard" i.e. the standard operating system animation will be applied. This value can be set to "none" which will mean the display switches immediately between landscape and portrait or vice versa.</p> <p>Note that the 'size' event listener should be used to detect the change in the display, as the 'orientation' change handlers pick up different sensors on some devices and may trigger independently of the display's orientation.</p>
--------------	--

Reference:	AIR-7121
Title:	Updating Android Gradle builds to AGP 8.4, minSdk 21, target 34
Applies to:	Android runtime components
Description:	The build system has been updated so that that Android runtime classes and native libraries are built using an Android 34 platform with Android Gradle Plug-in version 8.4. The minimum SDK is now 21 across all CPU variants.

Reference:	AIR-7139
Title:	Updating icon/banner sizes for Android TV applications
Applies to:	Core build tools
Description:	Android TV applications require slightly larger icon sizes for the different resolution / DPI variants. This change adds support for the necessary image sizes in the application descriptor file, as well as introducing new 'bannerXXXxYYY' variants for the banner images. ADT will now package the Android TV applications with appropriate files in the resource folders.

Reference:	AIR-7150
Title:	Android app descriptor elements for manifestPlaceholders
Applies to:	Core build tools
Description:	A new "manifestPlaceholders" element is available in the "android" section of the application descriptor file. This holds a list of "manifestPlaceholder" values that are used to set variables (for example, license keys or user/app specific settings) that could be required by third party libraries.



Reference:	AIR-7157
Title:	AIR Android support for display cut-out modes
Applies to:	Android runtime components and core build tools
Description:	<p>A new “displayCutoutMode” element is available in the “android” section of the application descriptor file. This is then used to provide the style for the application in how cut-outs are handled for full-screen applications. Values mirror those available on Android, default/always/never/shortEdges.</p> <p>See https://developer.android.com/develop/ui/views/layout/display-cutout#handle</p>

Reference:	AIR-7299
Title:	Adding configuration settings for ELS to control fallback and key storage
Applies to:	All runtime components, core build tools
Description:	<p>A new section in the application descriptor, called “encryptedLocalStorage”, can be used to specify how the user-specific key is stored (“storageMode”) and whether a fallback to older ELS mechanism is used (“fallbackMode”). These settings can be adjusted to prevent any possibility of operating system messages appearing asking for permissions or passwords.</p>

Reference:	AIR-7303
Title:	Compiler to support '\u{nnnnnn}' format for Unicode chars
Applies to:	AIR tools – package was omitted from 51.1.1.1 when downloaded via AIR SDK Manager, instead this fix would be in 51.1.1.4.
Description:	<p>The compiler for AS3 has been updated to support a “{nnnnnn}” format following the \u Unicode delimiter, in addition to the \unnnn format. The value in the brackets are hexadecimal but can be any character code in the Unicode range i.e. not limited to 0xFFFF. If a value higher is used, it will be encoded as two UTF-16 code points within the string.</p>

Reference:	AIR-7315
Title:	websocket to dispatch and respond to certificate errors



Applies to:	All runtime components
Description:	WebSocket clients use a SecureSocket internally, so this change hooks up the “certificateError” events that could be sent from that object, and passes it out from the WebSocket object. Event listeners can therefore call the ‘preventDefault’ function to allow connections to proceed despite the SSL certificate issue.

Reference:	Github-461 https://github.com/air sdk/Adobe-Runtime-Support/issues/461
Title:	Adding ADT handling and updating platform conversion for cmdline bundle
Applies to:	Desktop runtime components, core build tools
Description:	<p>Similar to a “bundle” target for ADT, a new “cmdline” option can be used to create command-line applications that have a captive AIR runtime, for the desktop operating systems. The applications that are then run will not generate a native window and cannot access any UI-related components. They can be quit either via a ctrl-c type command from the console/terminal, or within the application via NativeApplication.exit().</p> <p>Note that there appears to be an issue with the macOS command-line application so this will be investigated and a fix provided shortly.</p>

Reference:	Github-3297 https://github.com/air sdk/Adobe-Runtime-Support/issues/3297
Title:	Adding Android app descriptor settings for compileSdk and build tools folder
Applies to:	Core build tools
Description:	New application descriptor values within the “android” section allows for greater control over the build settings and environment used for Android APK/AAB creation. “androidCompileSdkVersion” is a number specifying the API level used for compilation; “androidBuildToolsVersion” is a version string specifying the build tools folder to use; note that the Android Gradle Plug-in behaviour changes in later versions such that this would be ignored and the latest available build tools always used.

Reference:	Github-3298 https://github.com/air sdk/Adobe-Runtime-Support/issues/3298
Title:	Adding support for iosimulator in the ADT configuration file
Applies to:	Core build tools

Description:	A new item has been added to the build configuration file, "iosSimulator", which can be set to one of the names of the available simulators that is available on the macOS device for installation and debugging an AIR app via the simulator.
--------------	--

Reference:	Github-3349 https://github.com/air sdk/Adobe-Runtime-Support/issues/3349
Title:	Adding '-compiler.float' option to turn off float support
Applies to:	AIR tools – package was omitted from 51.1.1.1 when downloaded via AIR SDK Manager, instead this fix would be in 51.1.1.4.
Description:	A new compiler option has been provided to ensure that new SWFs can be generated that do not have the "float" support, hence remaining compatible with other tools that interpret the ABC format without expecting a 'float' table in the constant pool.

Reference:	Github-3371 https://github.com/air sdk/Adobe-Runtime-Support/issues/3371
Title:	Android webview to allow file chooser dialogs in forms
Applies to:	Android runtime component
Description:	The WebView functionality has been updated to support the pass-through of file chooser requests, such that an HTML form can request a file or files which will result in the appropriate file picker dialog to be displayed by Android. Multiple files can be returned where this has been requested.

3.5 Bug Fixes

3.5.1 Release 51.1.1.1

Reference:	AIR-7142
Title:	Android OpenGL ES context is lost on device rotation
Applies to:	Android runtime component
Description:	When an Android device is rotated, the EGL context was being destroyed because of an issue with surface/size detection. However this appears to have been a historical issue, so the code has been updated so that it now attempts to retain the EGL context, meaning that all the GPU assets will be available following the display's orientation switch.

Reference:	AIR-7265
Title:	Enhanced ELS v2 file format with error checking
Applies to:	All runtime components
Description:	The format used to store ELS data has been updated so that it can include some error-checking for the decryption process. This will ensure that it can check that the correct application and user is accessing the file i.e. whether the decryption process actually created sensible results.

Reference:	Github-162 https://github.com/air sdk/Adobe-Runtime-Support/issues/162
Title:	Fixing rounding to ensure large scaled-down bitmaps display properly
Applies to:	All runtime components
Description:	An earlier fix had not completely fixed the issue where large but scaled-down bitmaps result in an arithmetic overflow with internal matrix operations in the AIR rendering code. This should complete the fix to allow this behaviour.

Reference:	Github-1494 https://github.com/air sdk/Adobe-Runtime-Support/issues/1494
Title:	Hooking up webview permission requests to existing PermissionManager implementations
Applies to:	All runtime components
Description:	When an embedded browser engine used by a WebView control is requesting permissions from the end user, this is now being redirected into the AIR application logic to check whether the application already has those permissions. If so, the appropriate response is sent to the webview control; if not, the user is prompted to grant/deny the permissions via the current PermissionManager mechanisms.

Reference:	Github-3307 https://github.com/air sdk/Adobe-Runtime-Support/issues/3307
Title:	Ensuring win32 webview loads an HTML-based AIR app via a FILE url
Applies to:	Windows runtime component

Description:	If a file path was used for loading a URL, on Windows with webview2 this had not been working due to some internal mechanisms for resolving paths. The fix means that URLs based on files or application URLs can now be used, rather than needing everything to be loaded via HTTP.
--------------	--

Reference:	Github-3310 https://github.com/air sdk/Adobe-Runtime-Support/issues/3310
Title:	Removing redundant webkit/FP files from AIR SDK
Applies to:	Various runtime components
Description:	Some of the unnecessary/obsolete files have been removed from the SDK.

Reference:	Github-3334 https://github.com/air sdk/Adobe-Runtime-Support/issues/3334
Title:	Correcting debugline values for 'getlex' instructions
Applies to:	AIR tools – package was omitted from 51.1.1.1 when downloaded via AIR SDK Manager, instead this fix would be in 51.1.1.4.
Description:	The compiler has been updated so that 'getlex' instructions are now included in the opcodes for which a 'debugline' value could be generated. This corrects some issues (typically during start-up/definition of classes) where an invalid debug line was shown.

Reference:	Github-3356 https://github.com/air sdk/Adobe-Runtime-Support/issues/3356
Title:	Fixing Array/Vector 'includes' method for strings created via parsing
Applies to:	All runtime components
Description:	An invalid object comparison type had meant that the 'includes' method for Arrays and Vector types was not working properly when used with strings that weren't directly equivalent (i.e. the underlying string storage might have been different). This should fix the comparisons to make them more match the idea of "indexOf(var) != -1"

Reference:	Github-3357 https://github.com/air sdk/Adobe-Runtime-Support/issues/3357
Title:	Preventing iOS crash when starting up with Scout

Applies to:	iOS runtime components
Description:	A recent update for native window handling had caused a problem when Adobe Scout was also present and configured to connect to a host computer during start-up. Additional defensive programming has been added to avoid the problem.

Reference:	Github-3360 https://github.com/airSDK/Adobe-Runtime-Support/issues/3360
Title:	Allowing file uploads from content URIs on Android
Applies to:	Android runtime component
Description:	Uploading a 'File' object to a web server using the FileReference API mechanisms was not working with 'content' URIs, i.e. files that have been selected from a file browser using the new Storage Access Framework. A number of changes have been added to enable this capability.

Reference:	Github-3370 https://github.com/airSDK/Adobe-Runtime-Support/issues/3370
Title:	Fixing Android ELS key being reset by AS3 call
Applies to:	Android runtime component
Description:	When 'reset' was called on Encrypted Local Storage, it was also removing the OS-specific storage used by the new ELS key store mechanism. The identifiers used for this have been updated to avoid this conflict.

3.5.2 Release 51.1.1.2

Reference:	Github-461 https://github.com/airSDK/Adobe-Runtime-Support/issues/461
Title:	Fixing command-line entry framework detection for MacOS bundle
Applies to:	MacOS runtime component
Description:	<p>The "cmdline" bundle creation on macOS was not correctly picking up the captive runtime, and had been falling back to rely on the installed (shared) runtime, which caused a versioning issues if different versions were used.</p> <p>The executable is now correctly looking first for the captive runtime framework in the same location as the executable.</p>

Reference:	Github-3380 https://github.com/airSDK/Adobe-Runtime-Support/issues/3380
Title:	Fixing Android file seek/tell functionality
Applies to:	Android runtime component
Description:	<p>A recent change to handle larger files on Android had caused problems when checking the file location or seeking within files that are also being read or written to. An initial change was made for files that were packaged in the APK file, as this was thought to be the cause of the problem, so these files are now being extracted and handled via Java/JNI calls.</p> <p>To complete the fix, the earlier code has been re-introduced, and where those functions fail (which should be in the case of the larger >2GB files) the newer code will be called. However it is not yet clear whether the new code actually does work properly in the case of large files; initial testing (for file writing) worked fine but complex cases may cause issues.</p>

Reference:	Github-3390 https://github.com/airSDK/Adobe-Runtime-Support/issues/3390
Title:	Fixing MacOS App Bundle packaging with ANE files for universal binaries
Applies to:	Core build tools
Description:	The change to allow MacOS application bundles to have their architecture specified led to a problem when packaging an application that contains ANEs (unless packaging for just x86_64). This has been updated so that the ANE platforms are correctly handled for all macOS platforms.

Reference:	Github-3391 https://github.com/airSDK/Adobe-Runtime-Support/issues/3391
Title:	Ensuring calls to navigateToUrl and sendToUrl still work with new x-air-appid header
Applies to:	All runtime components
Description:	The change in 51.1.1.1 to add an "x-air-appid" header to all URL requests had the side-effect of causing an internal error if calling navigateToUrl or sendToUrl. This header has now been added to the list of permissible headers when using those API calls.

3.5.3 Release 51.1.1.3

Reference:	Github-3354 https://github.com/air sdk/Adobe-Runtime-Support/issues/3354
Title:	Ensuring Chinese fonts on iOS 18 can be used
Applies to:	iOS runtime component
Description:	When running an existing AIR application on iOS 18 beta, Chinese characters were appearing as blank/square boxes. This was because AIR was not recognising the fonts as valid, because in iOS 18 they no longer contain a 'glyf' or 'CFF' table for the shape information. The code logic has been updated to accept the new Apple-proprietary table, so that the fonts can be used and passed to CoreGraphics for the text rendering.

Reference:	Github-3374 https://github.com/air sdk/Adobe-Runtime-Support/issues/3374
Title:	Correcting the aapt binary for Linux x86_64
Applies to:	Linux runtime component
Description:	The wrong binary had been included in the Linux version of the AIR SDK, with a macOS variant used for the "aapt" tool. The Linux x86_64 versions of these tools are now provided.

Reference:	Github-3375 https://github.com/air sdk/Adobe-Runtime-Support/issues/3375
Title:	Ensuring Touch End events are sent on iOS apps running on macOS
Applies to:	iOS runtime component
Description:	When an iOS app is run on an Apple-silicon macOS machine, the touch event handling did not cope properly with a 'right click' (double-finger tap) and a code logic error then prevented further processing of 'Touch End' events. This has been corrected; plus, to help identify the scenario where an iOS app is running on a mac, the "Capabilities.manufacturer" string will be updated to "Adobe macOS" rather than "Adobe iOS".

Reference:	Github-3402 https://github.com/air sdk/Adobe-Runtime-Support/issues/3402
Title:	Ensuring Android AppEntry debugger configuration is properly built into ADT



Applies to:	Core build tools
Description:	A code tidy-up task had resulted in the ADT build process not generating the correct code for the “debugger” version of AppEntry. This meant that Android applications could not be remote-debugged, when using the previous release. The build task has been updated to match the new code so that this is now working.

Reference:	Github-3403 https://github.com/air sdk/Adobe-Runtime-Support/issues/3403
Title:	Ensuring ELS getItem works on new machine with no fallback
Applies to:	All runtime components
Description:	As part of the ELS updates in 51.1, it is possible to specify to not use the earlier ELS storage mechanism as a fallback. However, a logic error in the code had assumed that if an item was not found in a new store, we could query the old store; when the old store is not available, this had been treated as an internal error. The logic has been updated here so that a missing item is no longer causing the code to throw an internal error exception.

Reference:	Github-3404 https://github.com/air sdk/Adobe-Runtime-Support/issues/3404
Title:	Moving ELS files into app-storage folders
Applies to:	All runtime components
Description:	The new ELS updates resulted in all ELS files being stored within a single Adobe-specific location in device storage. However, this does not follow standard practice for application-specific files, hence these files are being moved back into the “app-storage” folder.

3.5.4 Release 51.1.1.4

Reference:	AIR-7340
Title:	ANE loading information available when debugging
Applies to:	All runtime components



Description:	If a debugger is connected to a runtime, additional output will be provided when an ANE is loaded and when the initialize method is being called to list the method calls that are available. This is to aid in debugging of ANE-related problems.
--------------	--

Reference:	Github-3391 https://github.com/air sdk/Adobe-Runtime-Support/issues/3391
Title:	Improving ELS fallback capability, fixing key filestorage on mobile and ELS file writing on window
Applies to:	All runtime components
Description:	<p>The ELS functionality had still been causing problems, due to a number of the updates that had been going in under the 51.1 branch. This update follows a much wider set of testing of different scenarios and platforms including the upgrades from old applications and AIR versions, and should improve the functionality and robustness here.</p> <p>As well as fixing some of these scenarios, some fundamental issues were found and fixed, including the file storage location that had been used on mobile platforms for the ELS “user key”, and the file generation mechanism under the Windows platform.</p>

Reference:	Github-3394 https://github.com/air sdk/Adobe-Runtime-Support/issues/3394
Title:	Ensuring iOS worker asynchronous calls don't block the main UI thread
Applies to:	iOS runtime component
Description:	A recent update to fix a crash that had been happening within network callbacks had led to a deadlock situation when a Worker thread was making asynchronous calls (i.e. that should be asynchronous and yet not multi-threaded). The functionality has been updated to call back the asynchronous trigger in the isolate's main thread, rather than always using the primary/UI thread. This avoids the deadlock and allows the UI thread to continue.

Reference:	Github-3413 https://github.com/air sdk/Adobe-Runtime-Support/issues/3413
Title:	Ensuring NAIP uses command-line runtime option on Linux and Mac
Applies to:	Linux and macOS runtime components

Description:	The “naip” tool is used by ADT when creating application bundles, including for command-line apps. This is actually an AIR application though and had required a UI to be available i.e. running as a normal AIR app, with a window even though it was not made visible. Some changes have been made so that naip runs as a command-line app so that ADT and bundle creation can be done from headless terminals on Linux or macOS machines.
--------------	--

Reference:	Github-3418 https://github.com/air sdk/Adobe-Runtime-Support/issues/3418
Title:	Ensuring ld64 on old macOS versions doesn't use platform_version argument
Applies to:	Core build tools
Description:	The Apple linker options had changed a while ago with a new “platform_version” option being introduced and the older minimum version flags being removed. ADT had been updated for this but this prevented it from working properly with older macOS/Xcode installations that still used the original linker options and did not yet have support for “platform_version”. ADT now checks the linker version and uses the appropriate arguments.

Reference:	Github-3418 https://github.com/air sdk/Adobe-Runtime-Support/issues/3418
Title:	Updating compile-abc tool to run on macOS 10.13
Applies to:	iPhoneOS runtime component
Description:	The ‘compile-abc-64’ tool had been incorrectly built with settings to specify the minimum OS version as macOS 10.15. This has been changed so that the tools will run on 10.13 which is the earliest macOS version that the AIR SDK supports.

Reference:	Github-3419 https://github.com/air sdk/Adobe-Runtime-Support/issues/3419
Title:	Correcting default timestamp URL from symantec to digicert
Applies to:	Core build tools
Description:	A timestamp server was hard-coded into ADT for some of the package signing options – but this was using an old Symantec URL, which has recently been retired. This update changes this fallback value to use the replacement, from Digicert.



Reference:	Github-3434 https://github.com/air sdk/Adobe-Runtime-Support/issues/3434
Title:	Updating cacheAsBitmap max dimensions to use device/gpu capabilities
Applies to:	All runtime components
Description:	A failure of a sprite to display on Android when cacheAsBitmap was set was traced to a hard-coded value as a maximum for cached bitmaps on that platform. The code across all platforms has now been updated to check for the available texture dimensions (when using OpenGL ES) so that cacheAsBitmap requests are only rejected if the display object exceeds the device-specific limits.

Due to an error in the packaging information provided to the AIR SDK Manager, a number of earlier updates to the ActionScript Compiler would not be contained in releases prior to 51.1.1.4 if those were download via the SDK Manager – however, they would have been present in the SDK if downloaded as a monolithic zip file from our website.

Items affected by this problem are:

AIR-7303: Compiler to support '\u{nnnnn}' format for Unicode chars

Github-3334: Correcting debugline values for 'getlex' instructions

Github-3349: Adding '-compiler.float' option to turn off float support

These changes are in the "AIR Tools" component 3.1.0 released within the AIR SDK Manager in build 51.1.1.4.

3.5.5 Release 51.1.1.5

Reference:	AIR-7119
Title:	AIR Android - remove use of APIs that are restricted by strict mode
Applies to:	Android runtime component
Description:	Some APIs were triggering errors when running using 'strict' mode in Android; these have each been investigated, and eliminated either by removing the legacy code if it was not required/used now, or by adjusting the mechanism for using these.

Reference:	AIR-7354
Title:	ADT fails to package a macOS app bundle if default ANEs are needed



Applies to:	Core build tools
Description:	When a macOS bundle was being created using ANEs, the location of frameworks were being moved across to be in the correct place according to the macOS bundle structure requirements. However, if an ANE was used that didn't have a macOS platform-specific implementation, this was causing an error in the code which meant it failed but just silently skipped any remaining ANEs. The error handling has been moved and code updated so that missing macOS implementations do not cause any problems.

Reference:	AIR-7355
Title:	ADT fails to package Mac App Bundle
Applies to:	Core build tools
Description:	<p>This error had been introduced with the ability to run a mac packager via a command-line application, and was caused by the code used by the packager to create the ICNS file for the application icon.</p> <p>The runtime file may also be needed to complete this fix so this issue may still be present until the 51.2 release.</p>

Reference:	AIR-7360
Title:	Android AS3 keyboard mapping for Escape key events
Applies to:	Android runtime components
Description:	If using an external keyboard for Android, or when running Android on a PC, the "escape" key events were not being sent in to AS3. This was just an omission in some internal key code mapping and has been updated.

Reference:	Github-3330 https://github.com/airsdk/Adobe-Runtime-Support/issues/3330
Title:	Ensuring keyboard deactivation doesn't happen if a StageText element has focus
Applies to:	Android runtime component

Description:	A recent change to support NativeWindow on Android meant that when a window lost focus due to an auto-complete pop-up, the deactivation event meant that the soft keyboard was being deactivated. This flow has been updated to handle such conditions so that the soft keyboard behaviour works in a better way with these pop-ups.
--------------	--

Reference:	Github-3359 https://github.com/airSDK/Adobe-Runtime-Support/issues/3359
Title:	Updating FileStream async handling and Linux event loops
Applies to:	Linux runtime components
Description:	Some deadlock issues remained due to the way in which asynchronous functionality was implemented in conjunction with the Linux event loops; some issues in event registration/destruction also caused some stability issues with the runtime. The code has been reworked to properly handle the event loops and event deregistrations.

Reference:	Github-3391 https://github.com/airSDK/Adobe-Runtime-Support/issues/3391
Title:	Adding ELS recovery code following format issues in 51.0 stores
Applies to:	All runtime components
Description:	When the ELS format had been updated, some versions generated using 51.0 had a data structure that did not exactly match how information was stored from 51.1 onwards. This had caused problem for 51.1 to read these stores; however, there is enough information to recover the data so this is updated now to load properly a store created from 51.0.

Reference:	Github-3399 https://github.com/airSDK/Adobe-Runtime-Support/issues/3399
Title:	Reverting AIR-7115 to ensure keyboard display works better on Android TextField touch
Applies to:	Android runtime component
Description:	An earlier change that aimed to help the behaviour of Android TextFields (to allow scrolling of underlying content even if the touch event ended up in a TextField object) had caused a problem which prevented the soft keyboard from appearing unless the finger touch remained very still. The change has been reverted so fix this issue pending rework of that feature.



Reference:	Github-3414 https://github.com/airSDK/Adobe-Runtime-Support/issues/3414
Title:	Ensuring Android background thread can use recreated EGL surfaces
Applies to:	Android runtime components
Description:	With the improvements in EGL surface handling, some problems resulted from using the runtime in background thread mode because the EGL context then being accessed in the wrong thread. The updated calls to destroy and create the surfaces within the existing context have been modified to remain in the correct thread.

Reference:	Github-3460 https://github.com/airSDK/Adobe-Runtime-Support/issues/3460
Title:	Fixing EncryptedLocalStore.reset failure on windows
Applies to:	Window runtime component
Description:	On Window, the 'reset' call for Encrypted Local Store had been failing because of an internal platform restriction on the location of files when using the internal APIs. The appropriate updates have been added to ensure that the new ELS application-specific storage locations are flagged correctly as writable.

Reference:	Github-3467 https://github.com/airSDK/Adobe-Runtime-Support/issues/3467
Title:	Correcting Linux timezone offset to use ms
Applies to:	Linux runtime components
Description:	The TimeZone offset values should be in milliseconds; however on Linux these were provided in seconds, due to the underlying platform API used. This has been corrected to be consistent with other platforms.

Reference:	Github-3470 https://github.com/airSDK/Adobe-Runtime-Support/issues/3470
Title:	Correcting daylightSavingsOffset value for Linux
Applies to:	Linux runtime components



<p>Description:</p>	<p>The value used for the daylight savings had been set to zero on Linux when no daylight savings scheme was in use for a time zone. However according to the documentation, in this scenario the daylight savings offset value should just have been equal to the normal/raw offset. This has been fixed for Linux to bring this into line with the other platforms.</p>
---------------------	---

4 Configuration File

ADT uses an optional configuration file to change some of its behaviour. To create a configuration file (there is not one by default within the SDK), create a new text file and save this with the name “adt.cfg” in the SDK’s “lib” folder (i.e. alongside the ‘adt.jar’ file). The configuration file is in the standard ‘ini file’ format with separate lines for each option, written as “setting=value”. Current options are listed below:

Setting	Explanation
DefaultArch	Used as a default architecture if there is no “-arch” parameter provided to ADT. Values may be ‘armv8’, ‘armv8’, ‘x86’ or ‘x64’.
OverrideArch	Used where an architecture value is being provided to ADT using the ‘-arch’ parameter, this configuration setting will override such parameter with the value given here. Values may be ‘armv8’, ‘armv8’, ‘x86’ or ‘x64’.
DebugOut	If set to “true”, results in additional output being generated into a local file which can aid in debugging problems within ADT (including the use of third party tools from the Android SDK). Values may be ‘true’ or ‘false’, default is ‘false’.
UncompressedExtensions	A comma-separated list of file extensions that should not be compressed when such files are found in the list of assets to be packaged into the APK file. For example: “UncompressedExtensions=jpg,wav”
AddAirToAppID	Configures whether or not the “air.” prefix is added to an application’s ID when it is packaged into the APK. Values may be ‘true’ or ‘false’, default is ‘true’.
JavaXmx	Adjusts the maximum heap size available to the Java processes used when packaging Android apps (dx/d8, and javac). Default value is 1024m although this is automatically overridden by any environment variable or value passed to the originating application. If this config setting is present, e.g. ‘2048m’, then it takes priority over all other mechanisms.
CreateAndroidAppBundle	Overrides any usage of ADT with an APK target type, and instead generates an Android App Bundle. Note that the output filename is not adjusted so this may result in generation of a file with “.apk” extension even though it contains an App Bundle. Values may be ‘true’ or ‘false’, default is ‘false’.

KeepAndroidStudioOutput	<p>When generating an Android App Bundle, rather than using a temporary folder structure and cleaning this up, this option will generate the Android Studio file structure under the current folder and will leave this in place).</p> <p>Values may be 'true' or 'false', default is 'false'.</p>
AndroidPlatformSDK	<p>A path to the Android SDK, that can be used instead of the "-platformsdk" command line parameter. Note that on Windows, the path should contain either double-backslashes ("c:\\folder") or forwardslashes ("c:/folder").</p>
iOSPlatformSDK	<p>A path to the iOS/iPhone/iPhoneSimulator SDK, that can be used instead of the "-platformsdk" command line parameter.</p>
JAVA_HOME	<p>This can be set as an override or alternative to the system environment variable that is read when ADT needs to use Java (e.g. when creating an Android App Bundle). Note that on Windows, the path should contain either double-backslashes ("c:\\folder") or forwardslashes ("c:/folder").</p>
UseNativeCodesign	<p>On macOS, this will mean that the IPA binary is signed using the "codesign" process rather than using internal Java sun security classes within ADT. This is "false" by default, unless ADT detects that the sun security Java classes are not available.</p>
SignSwiftFiles	<p>By default, any swift libraries that are included in an IPA payload are signed in the normal way. This can be turned off by setting this value to "false".</p>
OnlyIncludeSwiftUsedArchsInSupport	<p>If this is set to "true" then for ipa-app-store builds that include a "SwiftSupport" folder, the swift libraries will be updated via lipo to only include architectures that are used by the application (e.g. armv7 and arm64, omitting armv7s and arm64e).</p>
OnlyIncludeSwiftUsedArchsInPayload	<p>This is similar to the above flag but applies to the versions of the swift libraries that are included in the "Payload" folder within the IPA package. This (and the above) are now defaulting to "false" so that the swift libraries are just copied into position, but to get the legacy behaviour this should be set to "true".</p>
iosSimulator	<p>The name of a simulator to use when installing or running an IPA file on an iPhone simulator on mac. Note that this value will be overridden by any command-line option or by an environment variable should this be set as well (i.e. AIR_IOS_SIMULATOR_DEVICE).</p>

5 Android builds

5.1 AAB Target

Google introduced a new format for packaging up the necessary files and resources for an application intended for uploading to the Play Store, called the Android App Bundle. Information on this can be found at <https://developer.android.com/guide/app-bundle>

AIR now supports the App Bundle by creating an Android Studio project folder structure and using Gradle to build this. It requires an Android SDK to be present and for the path to this to be passed in to ADT via the “-platformsdk” option (or set via a config file – it also checks in the default SDK download location). It also needs to have a JDK present and available, and will attempt to find this either from configuration files or via the JAVA_HOME environment variable (or if there is an Android Studio installation present in the default location, using the JDK provided by that).

To generate an Android App Bundle file, the ADT syntax is similar to the “apk” usage:

```
adt -package -target aab <signing options> output.aab <app descriptor and files> [-extdir <folder>] -platformsdk <path_to_android_sdk>
```

No “-arch” option can be provided, as the tool will automatically include all of the architecture types. Signing options are optional for an App Bundle.

Note that the creation of an Android App Bundle involves a few steps and can take significantly longer than creating an APK file. We recommend that APK generation is still used during development and testing, and the AAB output can be used when packaging up an application for upload to the Play Store.

ADT allows an AAB file to be installed onto a handset using the “-installApp” command, which wraps up the necessary bundletool commands that generate an APKS file (that contains a set of APK files suitable for a particular device) and then installs it. If developers want to do this manually, instructions for this are available at https://developer.android.com/studio/command-line/bundletool#deploy_with_bundletool, essentially the below lines can be used:

```
java -jar bundletool.jar build-apks --bundle output.aab --output output.apks --connected-device
```

```
java -jar bundletool.jar install-apks --apks=output.apks
```

Note that the APK generation here will use a default/debug keystore; additional command-line parameters can be used if the output APK needs to be signed with a particular certificate.

5.2 Play Asset Delivery

As part of an App Bundle, developers can create “asset packs” that are delivered to devices separately from the main application, via the Play Store. For information on these, please refer to the below link:

<https://developer.android.com/guide/playcore/asset-delivery>

In order to create asset packs, the application XML file needs to be modified within the <android> section, to list the asset packs and their delivery mechanism, and to tell ADT which of the files/folders being packaged should be put into which asset pack.

For example:

```
<assetPacks>
```

```
<assetPack id="ImageAssetPack" delivery="on-demand"
folder="AP_Images"/>
</assetPacks>
```

This instruction would mean that any file found in the "AP_Images" folder would be redirected into an asset pack with a name "ImageAssetPack". The delivery mechanisms can be "on-demand", "fast-follow" or "install-time" per the Android specifications.

Note that assets should be placed directly into the asset pack folder as required, rather than adding an additional "src/main/assets" folder structure that the Android documentation requires. This folder structure is created automatically by ADT during the creation of the Android App Bundle.

The asset pack folder needs to be provided as a normal part of the command line for the files that should be included in a package. So for example if the asset pack folder was "AP_Images" and this was located in the root folder of your project, the command line would be:

```
adt -package -target aab MyBundle.aab application.xml MyApp.swf AP_Images
[then other files, -platformsdk directive, etc]
```

If there were a number of asset packs and all of the relevant folders were found under an "AssetPacks" folder in the root of the project, the command line would be:

```
adt -package -target aab MyBundle.aab application.xml MyApp.swf -C
AssetsPacks . [then other files, -platformsdk directive, etc]
```

To access the asset packs via the Android Asset Pack Manager functionality, an ANE is available via the AIR Package Manager tool. See <https://github.com/airsdk/ANE-PlayAssetDelivery/wiki>

5.3 Android Text Rendering

Previously, the rendering of text on Android had been handled via a native library built into the C++-based AIR runtime file. This had some restrictions and issues with handling fonts, which caused major problems with Android 12 when the font fallback mechanism was changed and the native code no longer coped with this. To resolve this, a new text rendering mechanism has been implemented that uses public Android APIs in order to set up the fonts and to render the text.

The new mechanism uses JNI to communicate between the AIR runtime and the Android graphics classes for this, and has some differences with the legacy version. One of the changes that has been made is to correct the display of non-colored text elements when rendering to bitmap data: in earlier builds, if some text included an emoji with a fixed color (e.g. "flames" that are always yellow/orange even if you request a green font color) then these characters appeared blue, due to the different pixel formats used by Android vs the AIR BitmapData objects. With the new mechanism, AIR correctly renders these characters to BitmapData (although the problem still remains when rendering device text to a 'direct' mode display list).

Some developers may not want to switch to this new mechanism yet, and others may want their applications to always use it. Some would perhaps want it only when absolutely necessary i.e. from Android 12 onwards. To cope with this request, there is a new application descriptor setting that can be used: "<newFontRenderingFromAPI>" which should be placed within the <android> section of the descriptor XML. The property of this can be used to set the API version on which the new rendering mechanism takes place. The default value is API level 31 which corresponds to Android 12.0 (see <https://source.android.com/setup/start/build-numbers>). So for example if you always want devices to use the new mechanism, you can add:

```
<newFontRenderingFromAPI>0</newFontRenderingFromAPI>
```

whereas if you never want devices to use this, you could add:

```
<newFontRenderingFromAPI>99999</newFontRenderingFromAPI>
```

5.4 Android File System Access

In the earlier versions of Android, it was possible to use the filesystem in a similar way to a Linux computer, but with a set of restrictions that had a fairly high-level granularity:

- It was possible to read/write to an application's private storage location. AIR exposes this via `File.applicationStorageDirectory`.
- If the app requested the 'read/write storage' permission, the app could then read and write in the user's shared storage location and to removable storage. The main home folder was accessible via `File.userDirectory` or `File.documentsDirectory`, and later AIR 33.1 added `File.applicationRemovableStorageDirectory`.
- Later, this was updated such that the user had to also grant permission via a system pop-up message. To trigger this pop-up, AIR developers could use `File.requestPermission()`

With the introduction of "scoped storage" however, a lot of this has changed. Android files are treated in a similar way to other resources, with URLs using the "content://" schema which can refer either to filesystem-backed files, or to transient resources, or elements within other storage mechanisms such as databases and libraries. Permission to access each resource depends upon the creator of that resource, and by default it's not possible for an application to open a file that another application had created. Permissions for the top-level internal storage (i.e. `File.documentsDirectory`) have been changed so that applications cannot create entries here but must use sub-folders of these (a set of standard sub-folders is generally created by the OS).

Within AIR, we have been attempting to add support for the "content://" URLs, and to switch the File class "browseForXXX" functions so that they use the new intent-based mechanisms for selecting files to open and save, or to select a folder. Within these calls, we are also requesting the appropriate read/write permissions (and persisting these so that they can be used in the future). This means that it should be possible to call `browseForOpen()` and allow the user to select a shared file that can then always be opened (for reading). Equally a `browseForDirectory()` call should mean that an application then has read/write access into the selected directory and its sub-tree.

Requesting file system permissions has to be handled in a similar way, with permissions either granted for a file or for a folder tree. The `File.requestPermission()` function therefore looks at the native path of the File object this is called on, and decides whether to show a file open intent (if there's a normal path or URL in the `nativePath` property), or to show a folder selection intent (if the path ends in a forward-slash), or whether to just ignore the call with a 'granted' response and then wait for later permission requests for individual files (if the File object has not had a `nativePath` set). This last option is intended to allow apps to work across different Android versions and is the recommended option: early in the application lifecycle, create a new File and call `requestPermissions()`: if the app is running on an earlier Android version, the permission pop-up will appear, otherwise the app will need to request specific file access later on via the "browseForXXX" functions or by requesting permission for a specific file. Sadly it isn't possible to ensure that the user only gives a yes/no response for these file/folder open intents, they are able to browse for other files, so it may be that the file the user selects is not the one you are trying to open. If this is detected, the permission status event will show as 'denied', so if you are happy for the user to choose a different file, use `browseForOpen()` rather than `requestPermission()`.

There is an exception to having to use scoped storage and the storage access framework, which is if an application has the "MANAGE_EXTERNAL_FILES" permission. This permission is intended for utilities such as file manager apps and anti-virus scanners that have a legitimate need to access all the (shared storage) files on the device, but if an app requests this permission and is submitted to the Play Store, but doesn't justify itself, then the submission is likely to be rejected.

Some applications are not distributed via the Play Store though, at which point this permission can be used to turn the behaviour back to how it used to be in earlier Android versions. The



“`File.requestPermission()`” capability has been overridden in the cases where AIR detects this permission has been requested in the manifest, and it will now display the appropriate dialog to ask the user to turn on the ‘all files’ access for this app. Once this has been granted (asynchronously), it would then be possible to create, read and write files and folders including in the root storage device.

6 Windows builds

The SDK now includes support for Windows platforms, 32-bit and 64-bit. We recommend that developers use the “bundle” option to create an output folder that contains the target application. This needs to be packaged up using a third party installer mechanism, in order to provide something that can be easily distributed to and installed by end users. HARMAN are looking at adapting the previous AIR installer so that it would be possible for the AIR Developer Tool to perform this step, i.e. allowing developers to create installation MSI files for Windows apps in a single step.

Instructions for creating bundle packages are at:

https://help.adobe.com/en_US/air/build/WSfffb011ac560372f709e16db131e43659b9-8000.html

Note that 64-bit applications can be created using the “-arch x64” command-line option, to be added following the “-target bundle” option.

7 MacOS builds

MacOS builds are provided only as 64-bit versions. A limited shared runtime option is being prepared so that existing AIR applications can be used on Catalina, but the expectation for new/updated applications is to also use the “bundle” option to distribute the runtime along with the application, as per the above Windows section.

Note that Adobe’s AIR 32 SDK can be used on Catalina if the SDK is taken out of ‘quarantine’ status. For instructions please see an online guide such as:

<https://www.soccertutor.com/tacticsmanager/Resolve-Adobe-AIR-Error-on-MacOS-Catalina.pdf>

AIR SDK now supports MacOS Big Sur including on the new ARM-based M1 hardware: applications will be generated with ‘universal binaries’ and most of the SDK tools are now likewise built as universal apps.

8 iOS support

8.1 32-bit vs 64-bit

For deployment of AIR apps on iOS devices, the AIR Developer Tool will use the provided tools to extract the ActionScript Byte Code from the SWF files, and compile this into machine code that is then linked with the AIR runtime and embedded into the IPA file. The process of ahead-of-time compilation depends upon a utility that has to run with the same processor address size as the target architecture: hence to generate a 32-bit output file, it needs to run a 32-bit compilation process. This causes a problem on MacOS Catalina where 32-bit binaries will not run.

Additionally, due to the generation of stub files from the iPhone SDK that are used in the linking process – which are created in a similar, platform-specific way – it is not possible to create armv7-based stub files when using Catalina or later. From release 33.1.1.620, the stub files are based on iOS15 and are purely 64-bit. This means that no 32-bit IPAs can be generated, even when running on older macOS versions or on Windows.

8.2 MacOS remote linking from Windows

Due to a number of updates from Apple around the mach-o linker, and the movement of symbols between different component libraries, it has become increasingly problematic to link Apple binaries on a Windows computer. Originally, Adobe had cross-compiled the “ld64” Apple linker, but without support for the “TBD” format that Apple use for the iPhoneOS/AppleTVOS SDKs. To work around this limitation, the AIR SDK includes “stub” binaries for the SDKs – but it is not then possible to support the movement of symbols i.e. where a particular symbol is found in different frameworks for different iOS versions.

Using LLVM’s linker, which supports the mach-o format, it was also found that Apple restrictions had been preventing some applications from being published via the App Store due to a difference in how symbols were found/stored, and the known/unsupported issues in LLVM meant that this is also not a completely viable solution.

The solution that we will work with now is to use a mac machine to perform the link stage of the build process. The rest of the development and build process can still occur on Windows but linking the AIR application’s object files against the iPhone / AppleTV SDKs should be done on a mac.

There are two ways to achieve this: initially a manual mechanism to allow files to be pushed to a macOS machine, linked via a script, and then the result copied back to the Windows machine where the packaging command needs to be run again to pick up the binary. And with the release of 51.0.1 this is now possible to handle automatically within a single run of ADT, following some initial machine configuration. Details on these two methods follow.

8.2.1 Manual copying and linking

There are a number of steps to the build process in this scenario.

1. Configure ADT to use a specific folder, into which all linker inputs will be placed.

To do this, edit the “adt.cfg” file (in your home folder under an “.airsdk” subfolder) and add a line: “IPALinkFolder=c:/path/to/link/folder”. This must be the name of an existing folder, under which subfolders will be created for each run of ADT. Note that you need to use forward-slashes, or escaped backslashes (“\\”), due to how Java reads in property files.

2. Run your normal link command via ADT.

This will then generate a subfolder under your “IPALinkFolder” location, which contains a script file and all the input files needed for the Apple linker.

3. Copy this link folder to your macOS computer.

This can be done with SFTP/SCP or similar tools, or potentially you could have a network shared folder set up.

4. On the macOS computer, run the linker.

Using a terminal window, you will first need to set an environment variable, "AIR_SDK_HOME", and then run the script that was generated by ADT. For example:

```
export AIR_SDK_HOME=/Users/username/Downloads/AIR_SDK/AIRSDK_51.0.1
./linkerscript.sh
```

5. Copy the resulting file back onto the Windows PC.

The file should be called "linkerOutput" and should be an arm64 macho executable file.

6. Call ADT again, this time providing the linked file.

To do this, add the arguments "`-use-linker-output path_to_linkerOutput`"; this can go within the normal input files list, or at the end of this (similar to "`-extdir`").

ADT will then ignore the normal command to link the binary, and will use the provided executable in order to package and sign the IPA file.

7. Clean up.

The folder that's created under the "IPALinkFolder" location, as well as the linkerOutput file (and of course the files that have been copied to the macOS machine) are not automatically deleted. So these should be periodically cleaned up manually to avoid wasting disk space.

8.2.2 Programmatic remote linking

In order to automatically allow the Windows machine to connect to the macOS machine and to copy files and drive the linker, a password-less mechanism will need to be set up to allow remote access without any user interaction. This requires the use of SSH keys: unless a key-pair is created that doesn't have a passphrase, it will be necessary to use "ssh-agent" to store the passphrase and associate this with the user's Windows credentials.

To set this up (one time only):

1. Create a new key-pair (unless you want to use an existing pair).

On Windows, run "`ssh-keygen`" and provide a filename – the default is "id_rsa" but in this walkthrough we shall use "adt_access". It then prompts for a passphrase: if you leave this blank, you will not need to follow the "ssh agent" steps below, but the recommendation would be to create a suitably secure passphrase for this. You should then have two files, "adt_access" and "adt_access.pub".

2. Install the public key on the mac machine.

You can use `sftp/scp` for this. The key should be added into your ".ssh" folder – note that you need the username of the mac machine, which we shall assume is just "user". You will then need to configure SSH to allow this public key to be used for connections: if you remote in (or just open a terminal) on the mac, go into the ".ssh" folder, and run: "`cat adt_access.pub >> authorized_keys`". This adds the new key onto the end of the authorized keys list.

3. Set up ssh agent to provide the passphrase.

Firstly you will need to check that ssh-agent is running: open "Services" on the computer, and find an entry with name "OpenSSH Authentication Agent". This should be changed to "Automatic", or "Automatic (Delayed Start)" if you prefer, and if necessary, also started manually. The "Status" column should show that this is running.

Then in a Windows console, run “ssh-add adt_access” and provide your passphrase.

Note that if you get an error message “Permissions for 'private-key.ppk' are too open”, you will need to ensure that only the current user is able to access the private key file (“adt_access”). This means adjusting the “Security” properties on this file, changing the owner of the file to the current local user account, removing inheritance and inherited permissions, and removing all permissions for users/groups other than the current local user. For more details, see the below link:

[Windows SSH: Permissions for 'private-key' are too open - Super User](#)

You can then test the connection by running “ssh -i adt_access user@mac_ip_address”, which should then log on automatically without further prompting.

4. Provide the configuration to ADT.

Now that you have the connectivity set up, you need to create a configuration file for AIR. You will need to add two entries into the “adt.cfg” file that is in your “c:\users\username\airsdk\” folder:

```
IPALinkFolder=c:/path/to/link/folder
RemoteLinkMachine=mac_ip_address
```

The first setting is to provide a location into which the linker will output all of the files. This is not strictly necessary but will aid in debugging problems.

The second provides the network location of the remote machine onto which you’ve put the public ssh key.

You will then need to create a configuration file with the name of this “mac_ip_address” network address, with an “.cfg” extension, and put this into a subfolder “remote_link_configs” under the .airsdk directory. For example:

```
C:\Users\username\airsdk\remote_link_configs\192.168.1.3.cfg
```

The contents of this file should be:

```
CertPath=C:/path/to/private/key/adt_access
Username=user
SdkFolder=/Users/user/Documents/AIR_SDKs/AIRSDK_51.0.1
```

The “CertPath” value points to the private key that we’ve named “adt_access”, again please note the use of forward-slashes or double-backslashes in the Windows path. “Username” is the user associated with the key from when this was added to “authorized_keys”. And “SdkFolder” is the path on the remote mac machine where an AIR SDK can be found. This path is only used for the runtime libraries i.e. “libRuntimeHMAOT.arm-air.a” and “builtin_abc.arm64-air.o”, the linker won’t use this for the actual link binary (ld64) or the stub files; instead, the remote script picks up your iPhoneOS SDK using the “xcrun” utility.

Once that is all set up, you can use ADT as normal for IPA builds, and the remote linking will happen in the background. If there are issues, please check the adt.log (or use AIR SDK Manager’s “Troubleshooting” tab) and report an issue via Github.

Please do note that the link folders are not (currently) cleaned up with this approach, so the location under the “IPALinkFolder”, and its copy that is pushed to the remote Mac device (with the same name, within the user’s home folder) will still exist after the ADT process has completed. This will help with debugging any issues, but we expect to change this in the future.

9 Splash Screens

For our 'free tier' users, a splash screen is injected into the start-up of the AIR process, displaying the HARMAN and AIR logos for around 2 seconds whilst the start-up continues in the background. There are different mechanisms used for this on different platforms, the current systems are described below.

9.1 Desktop (Windows/macOS)

Splash screens are displayed in a separate window centred on the main display, while the start-up continues behind these. The processing of ActionScript is delayed until after the splash screen has been removed.

9.2 Android

The splash screen is displayed during start-up and happens immediately the runtime library has been loaded. After a slight delay the initial SWF file is loaded in and when processing for this starts, the splash screen is removed.

9.3 iOS

The splash screen is implemented as a launch storyboard with the binary storyboard and related assets included in the SDK. This has implications for those who are providing their own storyboards or images in an Assets.car file:

- If you are on the 'free tier' then the AIR developer tool will ignore any launch storyboard you have specified within your application descriptor file, or provided within the file set for packaging into the IPA file.
- If you are creating an Assets.car file, then you need to add in the AIR splash images from the SDK which are in the "lib/aot/res" folder. These should be copied and pasted into your ".xcassets" folder in the Xcode project that you are using for creation of your assets.

Troubleshooting:

Message from ADT: "warning: free tier version of AIR SDK will use the HARMAN launch storyboard" – this will be displayed if a <UILaunchStoryboardName> tag has been added via the AIR application descriptor file. The tag will be ignored and the Storyboard from the SDK will be used instead.

Message from ADT: "warning: removing user-included storyboard "[name]" will be displayed if there was a Storyboardc file that had been included in the list of files to package: this will be removed.

Message from ADT: "warning: free tier version of AIR SDK must use the HARMAN launch storyboard" – this will be displayed if the Storyboardc file in the SDK has been replaced by a user-generated one.

If a white screen is shown during start-up: check that the HARMAN splash images are included in your assets.car file. Note that the runtime may shut down if it doesn't detect the appropriate splash images.

The runtime may also shut down for customers with a commercial license if a storyboard has been specified within the AIR descriptor file but not added via the list of files to package into the IPA file.